

NAME

Log::Message::Simple

SYNOPSIS

```
use Log::Message::Simple qw[msg error debug
                             carp croak cluck confess];

use Log::Message::Simple qw[:STD :CARP];

### standard reporting functionality
msg(    "Connecting to database",          $verbose );
error(  "Database connection failed: $@",  $verbose );
debug(  "Connection arguments were: $args", $debug );

### standard carp functionality
carp(   "Wrong arguments passed: @_ " );
croak(  "Fatal: wrong arguments passed: @_ " );
cluck(  "Wrong arguments passed -- including stacktrace: @_ " );
confess("Fatal: wrong arguments passed -- including stacktrace: @_ " );

### retrieve individual message
my @stack = Log::Message::Simple->stack;
my @stack = Log::Message::Simple->flush;

### retrieve the entire stack in printable form
my $msgs  = Log::Message::Simple->stack_as_string;
my $trace = Log::Message::Simple->stack_as_string(1);

### redirect output
local $Log::Message::Simple::MSG_FH      = \*STDERR;
local $Log::Message::Simple::ERROR_FH   = \*STDERR;
local $Log::Message::Simple::DEBUG_FH   = \*STDERR;

### force a stacktrace on error
local $Log::Message::Simple::STACKTRACE_ON_ERROR = 1
```

DESCRIPTION

This module provides standardized logging facilities using the Log : Message module.

FUNCTIONS

msg("message string" [,VERBOSE])

Records a message on the stack, and prints it to STDOUT (or actually \$MSG_FH, see the GLOBAL VARIABLES section below), if the VERBOSE option is true. The VERBOSE option defaults to false.

Exported by default, or using the :STD tag.

debug("message string" [,VERBOSE])

Records a debug message on the stack, and prints it to STDOUT (or actually \$DEBUG_FH, see the GLOBAL VARIABLES section below), if the VERBOSE option is true. The VERBOSE option defaults to false.

Exported by default, or using the :STD tag.

error("error string" [,VERBOSE])

Records an error on the stack, and prints it to STDERR (or actually \$ERROR_FH, see the GLOBAL VARIABLES sections below), if the VERBOSE option is true. The VERBOSE options defaults to true.

Exported by default, or using the :STD tag.

carp();

Provides functionality equal to Carp:::carp() while still logging to the stack.

Exported by using the :CARP tag.

croak();

Provides functionality equal to Carp:::croak() while still logging to the stack.

Exported by using the :CARP tag.

confess();

Provides functionality equal to Carp:::confess() while still logging to the stack.

Exported by using the :CARP tag.

cluck();

Provides functionality equal to Carp:::cluck() while still logging to the stack.

Exported by using the :CARP tag.

CLASS METHODS**Log::Message::Simple->stack()**

Retrieves all the items on the stack. Since Log::Message::Simple is implemented using Log::Message, consult its manpage for the function retrieve to see what is returned and how to use the items.

Log::Message::Simple->stack_as_string([TRACE])

Returns the whole stack as a printable string. If the TRACE option is true all items are returned with Carp:::Longmess output, rather than just the message. TRACE defaults to false.

Log::Message::Simple->flush()

Removes all the items from the stack and returns them. Since Log::Message::Simple is implemented using Log::Message, consult its manpage for the function retrieve to see what is returned and how to use the items.

GLOBAL VARIABLES**\$ERROR_FH**

This is the filehandle all the messages sent to error() are being printed. This defaults to *STDERR.

\$MSG_FH

This is the filehandle all the messages sent to msg() are being printed. This default to *STDOUT.

\$DEBUG_FH

This is the filehandle all the messages sent to debug() are being printed. This default to *STDOUT.

\$STACKTRACE_ON_ERROR

If this option is set to true, every call to error() will generate a stacktrace using Carp:::shortmess(). Defaults to false

