
NAME

IO::Compress::RawDeflate - Write RFC 1951 files/buffers

SYNOPSIS

```
use IO::Compress::RawDeflate qw(rawdeflate $RawDeflateError) ;

my $status = rawdeflate $input => $output [,OPTS]
    or die "rawdeflate failed: $RawDeflateError\n";

my $z = new IO::Compress::RawDeflate $output [,OPTS]
    or die "rawdeflate failed: $RawDeflateError\n";

$z->print($string);
$z->printf($format, $string);
$z->write($string);
$z->syswrite($string [, $length, $offset]);
$z->flush();
$z->tell();
$z->eof();
$z->seek($position, $whence);
$z->binmode();
$z->fileno();
$z->opened();
$z->autoflush();
$z->input_line_number();
$z->newStream( [OPTS] );

$z->deflateParams();

$z->close() ;

$RawDeflateError ;

# IO::File mode

print $z $string;
printf $z $format, $string;
tell $z
eof $z
seek $z, $position, $whence
binmode $z
fileno $z
close $z ;
```

DESCRIPTION

This module provides a Perl interface that allows writing compressed data to files or buffer as defined in RFC 1951.

Note that RFC 1951 data is not a good choice of compression format to use in isolation, especially if you want to auto-detect it.

For reading RFC 1951 files/buffers, see the companion module *IO::Uncompress::RawInflate*.

Functional Interface

A top-level function, `rawdeflate`, is provided to carry out "one-shot" compression between buffers and/or files. For finer control over the compression process, see the *OO Interface* section.

```
use IO::Compress::RawDeflate qw(rawdeflate $RawDeflateError) ;
```

```
rawdeflate $input => $output [,OPTS]
    or die "rawdeflate failed: $RawDeflateError\n";
```

The functional interface needs Perl5.005 or better.

`rawdeflate $input => $output [, OPTS]`

`rawdeflate` expects at least two parameters, `$input` and `$output`.

The `$input` parameter

The parameter, `$input`, is used to define the source of the uncompressed data.

It can take one of the following forms:

A filename

If the `$input` parameter is a simple scalar, it is assumed to be a filename. This file will be opened for reading and the input data will be read from it.

A filehandle

If the `$input` parameter is a filehandle, the input data will be read from it. The string `'-'` can be used as an alias for standard input.

A scalar reference

If `$input` is a scalar reference, the input data will be read from `$$input`.

An array reference

If `$input` is an array reference, each element in the array must be a filename.

The input data will be read from each file in turn.

The complete array will be walked to ensure that it only contains valid filenames before any data is compressed.

An Input FileGlob string

If `$input` is a string that is delimited by the characters `"<"` and `">"` `rawdeflate` will assume that it is an *input fileglob string*. The input is the list of files that match the fileglob.

If the fileglob does not match any files ...

See *File::GlobMapper* for more details.

If the `$input` parameter is any other type, `undef` will be returned.

The `$output` parameter

The parameter `$output` is used to control the destination of the compressed data. This parameter can take one of these forms.

A filename

If the `$output` parameter is a simple scalar, it is assumed to be a filename. This file will be opened for writing and the compressed data will be written to it.

A filehandle

If the `$output` parameter is a filehandle, the compressed data will be written to it. The string `'-'` can be used as an alias for standard output.

A scalar reference

If \$output is a scalar reference, the compressed data will be stored in \$\$output.

An Array Reference

If \$output is an array reference, the compressed data will be pushed onto the array.

An Output FileGlob

If \$output is a string that is delimited by the characters "<" and ">" rawdeflate will assume that it is an *output fileglob string*. The output is the list of files that match the fileglob.

When \$output is an fileglob string, \$input must also be a fileglob string. Anything else is an error.

If the \$output parameter is any other type, undef will be returned.

Notes

When \$input maps to multiple files/buffers and \$output is a single file/buffer the input files/buffers will be stored in \$output as a concatenated series of compressed data streams.

Optional Parameters

Unless specified below, the optional parameters for rawdeflate, OPTS, are the same as those used with the OO interface defined in the *Constructor Options* section below.

AutoClose => 0|1

This option applies to any input or output data streams to rawdeflate that are filehandles.

If AutoClose is specified, and the value is true, it will result in all input and/or output filehandles being closed once rawdeflate has completed.

This parameter defaults to 0.

BinModeIn => 0|1

When reading from a file or filehandle, set binmode before reading.

Defaults to 0.

Append => 0|1

TODO

Examples

To read the contents of the file file1.txt and write the compressed data to the file file1.txt.1951.

```
use strict ;
use warnings ;
use IO::Compress::RawDeflate qw(rawdeflate $RawDeflateError) ;

my $input = "file1.txt";
rawdeflate $input => "$input.1951"
    or die "rawdeflate failed: $RawDeflateError\n";
```

To read from an existing Perl filehandle, \$input, and write the compressed data to a buffer, \$buffer.

```
use strict ;
use warnings ;
use IO::Compress::RawDeflate qw(rawdeflate $RawDeflateError) ;
use IO::File ;
```

```
my $input = new IO::File "<file1.txt"
    or die "Cannot open 'file1.txt': $!\n" ;
my $buffer ;
rawdeflate $input => \$buffer
    or die "rawdeflate failed: $RawDeflateError\n";
```

To compress all files in the directory "/my/home" that match "*.txt" and store the compressed data in the same directory

```
use strict ;
use warnings ;
use IO::Compress::RawDeflate qw(rawdeflate $RawDeflateError) ;

rawdeflate '</my/home/*.txt>' => '<*.1951>'
    or die "rawdeflate failed: $RawDeflateError\n";
```

and if you want to compress each file one at a time, this will do the trick

```
use strict ;
use warnings ;
use IO::Compress::RawDeflate qw(rawdeflate $RawDeflateError) ;

for my $input ( glob "/my/home/*.txt" )
{
    my $output = "$input.1951" ;
    rawdeflate $input => $output
        or die "Error compressing '$input': $RawDeflateError\n";
}
```

OO Interface

Constructor

The format of the constructor for IO::Compress::RawDeflate is shown below

```
my $z = new IO::Compress::RawDeflate $output [,OPTS]
    or die "IO::Compress::RawDeflate failed: $RawDeflateError\n";
```

It returns an IO::Compress::RawDeflate object on success and undef on failure. The variable \$RawDeflateError will contain an error message on failure.

If you are running Perl 5.005 or better the object, \$z, returned from IO::Compress::RawDeflate can be used exactly like an *IO::File* filehandle. This means that all normal output file operations can be carried out with \$z. For example, to write to a compressed file/buffer you can use either of these forms

```
$z->print("hello world\n");
print $z "hello world\n";
```

The mandatory parameter \$output is used to control the destination of the compressed data. This parameter can take one of these forms.

A filename

If the \$output parameter is a simple scalar, it is assumed to be a filename. This file will be opened for writing and the compressed data will be written to it.

A filehandle

If the \$output parameter is a filehandle, the compressed data will be written to it. The string '-' can be used as an alias for standard output.

A scalar reference

If \$output is a scalar reference, the compressed data will be stored in \$\$output.

If the \$output parameter is any other type, IO::Compress::RawDeflate::new will return undef.

Constructor Options

OPTS is any combination of the following options:

AutoClose => 0|1

This option is only valid when the \$output parameter is a filehandle. If specified, and the value is true, it will result in the \$output being closed once either the close method is called or the IO::Compress::RawDeflate object is destroyed.

This parameter defaults to 0.

Append => 0|1

Opens \$output in append mode.

The behaviour of this option is dependent on the type of \$output.

* A Buffer

If \$output is a buffer and Append is enabled, all compressed data will be append to the end of \$output. Otherwise \$output will be cleared before any data is written to it.

* A Filename

If \$output is a filename and Append is enabled, the file will be opened in append mode. Otherwise the contents of the file, if any, will be truncated before any compressed data is written to it.

* A Filehandle

If \$output is a filehandle, the file pointer will be positioned to the end of the file via a call to seek before any compressed data is written to it. Otherwise the file pointer will not be moved.

This parameter defaults to 0.

Merge => 0|1

This option is used to compress input data and append it to an existing compressed data stream in \$output. The end result is a single compressed data stream stored in \$output.

It is a fatal error to attempt to use this option when \$output is not an RFC 1951 data stream.

There are a number of other limitations with the Merge option:

- 1 This module needs to have been built with zlib 1.2.1 or better to work. A fatal error will be thrown if Merge is used with an older version of zlib.
- 2 If \$output is a file or a filehandle, it must be seekable.

This parameter defaults to 0.

-Level

Defines the compression level used by zlib. The value should either be a number between 0 and 9 (0 means no compression and 9 is maximum compression), or one of the symbolic constants defined below.

Z_NO_COMPRESSION

```
Z_BEST_SPEED
Z_BEST_COMPRESSION
Z_DEFAULT_COMPRESSION
```

The default is Z_DEFAULT_COMPRESSION.

Note, these constants are not imported by IO::Compress::RawDeflate by default.

```
use IO::Compress::RawDeflate qw(:strategy);
use IO::Compress::RawDeflate qw(:constants);
use IO::Compress::RawDeflate qw(:all);
```

-Strategy

Defines the strategy used to tune the compression. Use one of the symbolic constants defined below.

```
Z_FILTERED
Z_HUFFMAN_ONLY
Z_RLE
Z_FIXED
Z_DEFAULT_STRATEGY
```

The default is Z_DEFAULT_STRATEGY.

Strict => 0|1

This is a placeholder option.

Examples

TODO

Methods

print

Usage is

```
$z->print($data)
print $z $data
```

Compresses and outputs the contents of the \$data parameter. This has the same behaviour as the print built-in.

Returns true if successful.

printf

Usage is

```
$z->printf($format, $data)
printf $z $format, $data
```

Compresses and outputs the contents of the \$data parameter.

Returns true if successful.

syswrite

Usage is

```
$z->syswrite $data
$z->syswrite $data, $length
$z->syswrite $data, $length, $offset
```

Compresses and outputs the contents of the `$data` parameter.

Returns the number of uncompressed bytes written, or `undef` if unsuccessful.

write

Usage is

```
$z->write $data
$z->write $data, $length
$z->write $data, $length, $offset
```

Compresses and outputs the contents of the `$data` parameter.

Returns the number of uncompressed bytes written, or `undef` if unsuccessful.

flush

Usage is

```
$z->flush;
$z->flush($flush_type);
```

Flushes any pending compressed data to the output file/buffer.

This method takes an optional parameter, `$flush_type`, that controls how the flushing will be carried out. By default the `$flush_type` used is `Z_FINISH`. Other valid values for `$flush_type` are `Z_NO_FLUSH`, `Z_SYNC_FLUSH`, `Z_FULL_FLUSH` and `Z_BLOCK`. It is strongly recommended that you only set the `flush_type` parameter if you fully understand the implications of what it does - overuse of `flush` can seriously degrade the level of compression achieved. See the `zlib` documentation for details.

Returns true on success.

tell

Usage is

```
$z->tell()
tell $z
```

Returns the uncompressed file offset.

eof

Usage is

```
$z->eof();
eof($z);
```

Returns true if the `close` method has been called.

seek

```
$z->seek($position, $whence);
seek($z, $position, $whence);
```

Provides a sub-set of the `seek` functionality, with the restriction that it is only legal to seek forward in the output file/buffer. It is a fatal error to attempt to seek backward.

Empty parts of the file/buffer will have NULL (0x00) bytes written to them.

The `$whence` parameter takes one the usual values, namely `SEEK_SET`, `SEEK_CUR` or

SEEK_END. Returns 1 on success, 0 on failure.

binmode

Usage is

```
$z->binmode  
binmode $z ;
```

This is a noop provided for completeness.

opened

```
$z->opened()
```

Returns true if the object currently refers to a opened file/buffer.

autoflush

```
my $prev = $z->autoflush()  
my $prev = $z->autoflush(EXPR)
```

If the \$z object is associated with a file or a filehandle, this method returns the current autoflush setting for the underlying filehandle. If EXPR is present, and is non-zero, it will enable flushing after every write/print operation.

If \$z is associated with a buffer, this method has no effect and always returns undef.

Note that the special variable \$| **cannot** be used to set or retrieve the autoflush setting.

input_line_number

```
$z->input_line_number()  
$z->input_line_number(EXPR)
```

This method always returns undef when compressing.

fileno

```
$z->fileno()  
fileno($z)
```

If the \$z object is associated with a file or a filehandle, this method will return the underlying file descriptor.

If the \$z object is associated with a buffer, this method will return undef.

close

```
$z->close() ;  
close $z ;
```

Flushes any pending compressed data and then closes the output file/buffer.

For most versions of Perl this method will be automatically invoked if the IO::Compress::RawDeflate object is destroyed (either explicitly or by the variable with the reference to the object going out of scope). The exceptions are Perl versions 5.005 through 5.00504 and 5.8.0. In these cases, the close method will be called automatically, but not until global destruction of all live objects when the program is terminating.

Therefore, if you want your scripts to be able to run on all versions of Perl, you should call close explicitly and not rely on automatic closing.

Returns true on success, otherwise 0.

If the `AutoClose` option has been enabled when the `IO::Compress::RawDeflate` object was created, and the object is associated with a file, the underlying file will also be closed.

newStream([OPTS])

Usage is

```
$z->newStream( [OPTS] )
```

Closes the current compressed data stream and starts a new one.

`OPTS` consists of any of the the options that are available when creating the `$z` object.

See the *Constructor Options* section for more details.

deflateParams

Usage is

```
$z->deflateParams
```

TODO

Importing

A number of symbolic constants are required by some methods in `IO::Compress::RawDeflate`. None are imported by default.

`:all`

Imports `rawdeflate`, `$RawDeflateError` and all symbolic constants that can be used by `IO::Compress::RawDeflate`. Same as doing this

```
use IO::Compress::RawDeflate qw(rawdeflate $RawDeflateError
:constants) ;
```

`:constants`

Import all symbolic constants. Same as doing this

```
use IO::Compress::RawDeflate qw(:flush :level :strategy) ;
```

`:flush`

These symbolic constants are used by the `flush` method.

```
Z_NO_FLUSH
Z_PARTIAL_FLUSH
Z_SYNC_FLUSH
Z_FULL_FLUSH
Z_FINISH
Z_BLOCK
```

`:level`

These symbolic constants are used by the `Level` option in the constructor.

```
Z_NO_COMPRESSION
Z_BEST_SPEED
Z_BEST_COMPRESSION
Z_DEFAULT_COMPRESSION
```

:strategy

These symbolic constants are used by the `Strategy` option in the constructor.

`Z_FILTERED`
`Z_HUFFMAN_ONLY`
`Z_RLE`
`Z_FIXED`
`Z_DEFAULT_STRATEGY`

For

EXAMPLES

TODO

SEE ALSO

`Compress::Zlib`, `IO::Compress::Gzip`, `IO::Uncompress::Gunzip`, `IO::Compress::Deflate`,
`IO::Uncompress::Inflate`, `IO::Uncompress::RawInflate`, `IO::Compress::Bzip2`,
`IO::Uncompress::Bunzip2`, `IO::Compress::Lzop`, `IO::Uncompress::UnLzop`, `IO::Compress::Lzf`,
`IO::Uncompress::UnLzf`, `IO::Uncompress::AnyInflate`, `IO::Uncompress::AnyUncompress`

`Compress::Zlib::FAQ`

`File::GlobMapper`, `Archive::Zip`, `Archive::Tar`, `IO::Zlib`

For RFC 1950, 1951 and 1952 see <http://www.faqs.org/rfcs/rfc1950.html>,
<http://www.faqs.org/rfcs/rfc1951.html> and <http://www.faqs.org/rfcs/rfc1952.html>

The `zlib` compression library was written by Jean-loup Gailly gzip@prep.ai.mit.edu and Mark Adler
madler@alumni.caltech.edu.

The primary site for the `zlib` compression library is <http://www.zlib.org>.

The primary site for `gzip` is <http://www.gzip.org>.

AUTHOR

This module was written by Paul Marquess, pmqs@cpan.org.

MODIFICATION HISTORY

See the `Changes` file.

COPYRIGHT AND LICENSE

Copyright (c) 2005-2007 Paul Marquess. All rights reserved.

This program is free software; you can redistribute it and/or modify it under the same terms as Perl itself.